

BODYCRAFT HOW TO UPDATE LCD TREADMILL

THINGS YOU'LL NEED:


1. USB DRIVE
(FAT32 & 2.0 OR ABOVE)
2. COMPUTER



STEP 1: PLUG USB DRIVE INTO COMPUTER.



STEP 2: VISIT BODYCRAFT.COM & CLICK ON "CUSTOMER SUPPORT" AT THE BOTTOM OF THE PAGE.



STEP 3: SCROLL DOWN TO "EPROM UPDATE" AND SELECT YOUR CONSOLE. THE DOWNLOAD SHOULD BEGIN.

SOFTWARE UPDATES:

Need to update the software on your Blu-View, Touch Screen Console or T-Series Treadmill?

For LCD7 Blu-View models: R200, R400g, SCT400g, ECT400g, ECT800g [Click here to Download LCD7 Ver.1.4](#)
For TOUCH7 Color Touch Screen models: ECT500g, ECT1000g, U1000g, R1000g [Click here to Download Touch 7 Ver.0.41](#)

For 2015-19 T-Series Treadmills (Serial Number MUST begin with TR). [Click here for Programming & Calibration Procedure](#).

T400 (Serial Number begins with TR41) [Click here to Download T400 Update](#)

T800 (Serial Number begins with TR81) [Click here to Download T800 Update](#)

T1000 (Serial Number begins with TR1K) [Click here to Download T1000 Update](#)

For 2019+ T-Series Treadmills (Serial Number MUST begin with T401, T801, and T1K1).

There are 3 Consoles available for each of the 3 Treadmill bases. Each Treadmill and Console has its own model and serial number; so the update is based on the model number of the console and NOT the Model number of the treadmill base. Use the console serial number info below to ID the console model.

[Click here for PDF software installation instructions](#) or [Click here to watch the software installation video](#).

T-9LCD for T400, T800 & T1000 (Serial Number begins with 9LCD) [Click here to download T-9LCD Ver. 2019K2U2V20](#)

T-10TS for T400, T800 & T1000 (Serial Number begins with 10TS) [Click here to download T-10TS Update Ver. 20191120V30](#)

T-16TS for T400, T800 & T1000 (Serial Number begins with 16TS) [Click here to Download T-16TS Update Ver. 20191120V30](#)



STEP 4: LOCATE THE FILE IN YOUR DOWNLOADS FOLDER. BE SURE THE FILE NAME IS "AA01770.BIN" FOR 9 INCH LCD DO NOT TRY TO OPEN FILE.

STEP 5: CLICK AND DRAG THE FILE FROM THE DOWNLOADS FOLDER TO YOUR USB DRIVE TO COPY IT.

STEP 6:

ONCE THE FILE IS COPIED TO THE USB DRIVE. SAFELY REMOVE THE USB BY RIGHT CLICKING ON IT & EJECTING IT.



STEP 10:

SELECT "ENTER" TO BEGIN THE SOFTWARE UPDATE



STEP 7:

PLUG USB INTO THE PORT ON THE CONSOLE.



STEP 11:

THE SOFTWARE UPDATE WILL AUTOMATICALLY RUN. WHEN IT'S FINISHED THE CONSOLE WILL RETURN TO THE IDLE MODE.



STEP 8:

PRESS AND HOLD THE "INCLINE+ & INCLINE-" ON THE CONSOLE UNTIL ENGINEER MODE IS ACTIVATED.



STEP 12:

REMOVE THE USB DRIVE AND YOU'RE DONE!



STEP 9:

THE MESSAGE WILL SHOW "SW UPDATE--YES".

